1. Introduction

The Differential Microwave Radiometers (DMR) experiment, one of the three scientific experiments aboard the COsmic Background Explorer (COBE, see [1]), was designed to obtain definitive measurements of the anisotropy of the cosmic microwave background (CMB) radiation.

The Initial Product Data Sets include six DMR full sky maps at 31.5, 53, and 90 GHz with two independent channels at each frequency, and in addition differential data sorted by sky position to provide sky sampling information. The sky maps are in Ecliptic coordinates. Products for four of the channels (53 and 90 GHz, channel A and B) consist of data obtained during the first full year of the operation (1989 day 356 to 1990 day 355). Products for the other two channels (31 GHz, channel A and B) consist of data obtained during the same time period excluding the eclipse season (1990 day 141 to 1990 day 206). Here the eclipse season refers to the period when COBE moves through the Earth's shadow as the spacecraft passes over the South Pole. The data sets are in the Flexible Image Transport System (FITS) format.

2. DMR Instrument Description

A. The Differential Microwave Radiometers

The DMR instrument was designed to map the CMB intensity on large angular scales. The instrument is described in detail in [2]. The instrument consists of six differential microwave radiometers, two independent radiometers which operate at each of three frequencies: 31.5, 53, and 90 GHz. These frequencies were chosen to be near the minimum of the Galactic emission spectrum and near the CMB peak. The multiple frequency measurements provide the ability to separate Galactic emission from cosmic emission based on spectral shape and to measure the spectrum of detected anisotropies.

The DMR instrument measures the difference in power received from two directions separated by 60 degrees on the sky. Each horn antenna has a field of view which is approximately a seven degree FWHM Gaussian (see [3]). The COBE Satellite is in a 900 km altitude, near-polar (99 degree inclination) orbit which precesses to follow the terminator. Over six months the combination of the 0.8-rpm spacecraft spin, 103-minute orbit, and 1 degree-per-day orbital precession enable DMR antennae to make highly-redundant observations of the entire sky. Noise level per measurement (0.5 sec being the duration of a measurement) for each DMR channel can be found in Table 2.1.

Table 2.1 Noise Level (per 0.5 sec measurement) for Each DMR Channel

Channel	31A	31B	53A	53B	90A	90B
Nominal RMS (mK)	55.0	58.3	22 . 5	24.9	40.3	28.3

B. Calibration

Three techniques are used to assure the accurate calibration of the DMR instrument. First, the signal difference between beam-filling hot and cold targets observed on the ground provides a primary calibration that is transferred to space by noise sources internal to the instrument. Second, the Moon is used in flight as an external calibration source. Third, the signal arising from the Doppler effect due to the Earth's motion around the barycenter of the solar system is used as an external calibration source. Preliminary analysis of the external source calibration techniques confirms the accuracy of the currently more precise ground-based calibration. A detailed description of various calibration techniques can be found in [4].

3. Data Reduction

A. Overview

COBE data are digitized and stored in an on-board tape recorder before being telemetered daily to a ground station. A pre-processor strips the DMR data from the telemetry stream, merges the raw DMR data with spacecraft attitude and orbit information, and checks the quality of the data, flagging data known or suspected to be unusable. A slowly-varying baseline is removed and the data are calibrated. The calibrated data are then corrected for various instrumental and systematic effects and used to make sky maps.

B. Processing Leading to Initial Products

We combine the original DMR telemetry data with spacecraft attitude and orbit information to create a Time-Ordered Data Set. The data are then scanned for various sources of contamination and data quality flags are set. We reject data of questionable telemetry quality, data without accompanying attitude information, or with the instrument science telemetry disabled. We also reject spikes and transients in the data, disgarding all points that lie more than five times the RMS scatter from the daily mean.

An instrumental offset is modeled using a slowly-varying baseline fit to the uncalibrated data and then subtracted. Three different fitting functions, a cubic spline, a Legendre polynomial, and a running mean, were used and the results were checked for consistency. Then a calibration factor is applied to convert the data from digitized telemetry units to antenna temperature.

The calibrated data were corrected for various known effects: the

satellite's motion around the Earth (7.4 km/s); the Earth's motion around the solar system barycenter (30 km/s); the magnetic susceptibility of the instrument; emission from the moon picked up in the antenna sidelobes and emission from Jupiter. For a detailed account of the systematic error corrections see [5] and [6].

The calibrated, corrected data are fitted to sky maps with 6144 pixels (2.8 degree angular size) whose independent antenna temperatures are chosen to minimize the Chi-squared sum,

Chi-squared = SUM (Ti-Tj-DTij)^2 / (sigma ij)^2

where the sum is over all observations, Ti and Tj are the map temperatures at pixels i and j, and DTij and sigma_ij are the measured temperature differences between pixels i and j and their associated errors respectively. Since the antenna beam width is larger than the pixel size, there is some correlation between neighboring pixels for any real signal. Further details of the data processing algorithms are described in [7] and [8].

4. Initial Products

A. DMR Pixelized Differential Data

The corrected, calibrated time-ordered data have been sorted according to the pixel number seen by horn 1, and then by the pixel number seen by horn 2. All differential measurements for a given pixel pair are then combined into four statistics: the sums of the first to fourth powers of the differential temperatures. These sums, the horn 1 and horn 2 pixel numbers, and the number of occurrences of each pixel permutation comprise the DMR pixelized differential data. For each channel, there are over a million pixel permutations. The data record format for each pixel permutation is given in Table 4.1.

A simple program PIXPRM, listed in Appendix 1, can be used to read the FITS binary table from the DMR pixelized Initial Product. This FORTRAN example uses the FITSIO library and should run, as written, on all platforms on which the library is supported. FITSIO was written by William Pence of NASA GSFC HEASARC, and is available by anonymous FTP from tetra.gsfc.nasa.gov. For illustrative purposes, the example calculates some simple statistics from the data sets; users may wish to substitute their own code to perform the calculations in which they are interested.

Table 4.1 DMR Pixelized Differential Data Set

Data field	Description
PIX_PLUS PIX_MINU N_OBS SUM SUM_2 SUM_3 SUM_4	Pixel number (0 to 6143) for horn 1 Pixel number (0 to 6143) for horn 2 Number of observations SUM (differential temperatures) (mK) SUM (differential temperatures)^2 (mK^2) SUM (differential temperatures)^3 (mK^3) SUM (differential temperatures)^4 (mK^4)

B. DMR Sky Maps

A sky temperature for each pixel on the sky maps is derived by solving a linear system of equations to the DMR observations by minimizing the chi-squared, while simultaneously fitting the coefficients of systematic error models. The resulting sky maps represent temperature differences; chi-squared is unchanged by the addition of an arbitrary constant to the map. The data record format for each pixel of the sky map is given in Table 4.2. The maximum, mean, and minimum sky map coverages and the corresponding pixel-to-pixel RMS noise levels are given in Table 4.3. More information about the type of baseline used and various systematic error corrections applied can be found in the FITS header.

A simple program SKYMAP, listed in Appendix 2, can be used to read the FITS binary table from the DMR sky map Initial Product. This FORTRAN program also uses the FITSIO library as described in 4.A.

Table 4.2 DMR Sky Maps Data Set

Data field	Description
PIXEL SIGNAL N_OBS SERROR ECLON ECLAT GALON GALAT	Pixel number (0 to 6143) Sky antenna temperature (mK) Number of observations Estimate of uncertainty as RMS/SQRT(N_OBS) (mK) Ecliptic longitude (degrees) Ecliptic latitude (degrees) Galactic longitude (degrees) Galactic latitude (degrees)
RA DEC	Right ascension (degrees) Declination (degrees)

Table 4.3 DMR Sky Map Coverage and Sensitivity Limits

DMR Channel	31A	======= 31B	53A	======= 53B	90A	90B	=
Max obs/pixel Noise level(mK)	36178 0.289	35720 0.309	41063 0.111	41218 0.123	40711 0.200	40713 0.140	_
Mean obs/pixel	14612	14076	17433	17434	17337	17325	
Noise level(mK)	0.455	0.492	0.170	0.223	0.306	0.215	
Min obs/pixel	5306	4205	8881	8896	8825	8853	
Noise level(mK)	0.755	0.900	0.238	0.263	0.429	0.300	

References:

- [1] The COBE Mission: Its Design and Performance Two Years After Launch, N.W. Boggess et al. 1992, APJ, 420
- [2] COBE Differential Microwave Radiometers: Instrument Design and Implementation, G.F.Smoot et al. 1990, APJ, 360, 685
- [3] Measurements of Very Low-sidelobe Conical Horn Antennas, Marco A. Toral et al. 1989, IEEE Transactions on Antennas and Propagation, Vol 37, No.2.
- [4] COBE Differential Microwave Radiometers(DMR): Calibration Techniques, C.L.Bennett et al. 1992, APJ, 391
- [5] Daily Quality Assurance Software for a Satellite Radiometer System, P.B. Keegstra et al., Proceedings of the 1st Astronomical Data Analysis and Software Systems Conference, PASP Conference Series, 25(1991): 3 p.
- [6] COBE Differential Microwave Radiometers (DMR): Preliminary Systematic Error Analysis, A. Kogut et al. 1992, APJ, 401
- [7] COBE Differential Microwave Radimeter (DMR) Data Processing Techniques, P.D. Jackson et al., Proceedings of the 1st Astronomical Data Analysis and Software Systems Conference, PASP Conference Series, 25(1991): 3 p.
- [8] Mapping the Sky with the COBE Differential Microwave Radiometers, M.A. Janssen and S. Gulkis, Proceedings of Infrared and Submillimetre Sky After COBE, 1992.

```
program pixprm
С
        A simple program to read the FITS binary table from the DMR
С
        pixelized Initial Product.
        integer maxdim
        parameter (maxdim = 20)
        character*30 errtxt, extnam,
     &
                      ttype (maxdim),
                      tform(maxdim),
     &
                      tunit(maxdim)
     &
        logical simple, extend, anyflg
        integer iunit, status, bitpix, naxis, naxes (maxdim), pcount, gcount
        integer group,fpixel,nelem,nrows
        integer i, j, nobs, nperm, npoint
        integer tfield, rwstat, bksize, vardat
        integer colnum, frow, felem
        integer hdutyp, inull
        real
                sum, sum2, enull
        doubleprecision sumsum, sum sq
        status=0
        iunit=15
        open the existing FITS file with readonly access
С
        rwstat=0
        call ftopen(iunit,'dmr pixperm 31a.fits',rwstat,bksize,status)
        if (status .ne. 0) goto 99
С
        read the required primary array keywords
        call ftghpr(iunit, maxdim, simple, bitpix, naxis, naxes,
                     pcount, gcount, extend, status)
        if (status .ne. 0) goto 99
C
        now move to the binary table extension
        call ftmahd(iunit, 2, hdutyp, status)
        if (status .ne. 0) goto 99
С
        get the binary table parameters
        call ftghbn(iunit, maxdim, nrows, tfield, ttype, tform, tunit,
                     extnam, vardat, status)
     γ
        if (status .ne. 0) goto 99
С
        test that this is a DMR pixperm dataset, and its fields
        are as expected.
        if (extnam .ne. 'DMR PIXPERM' .or.
            ttype(4) .ne. 'SUM'
     λ
            ttype(5) .ne. 'SUM 2' .or.
     &
            ttype(3) .ne. 'N OBS') then
```

```
print *, 'extnam = ', extnam
          print *, 'ttype(4) = ', ttype(4)
          print *, 'ttype(5) = ', ttype(5)
          print *, 'ttype(3) = ', ttype(3)
          stop 'Not a DMR pixperm dataset.'
        endif
С
        initialize statistical accumulators
        nperm = 0
        npoint = 0
        sumsum = 0.0d0
        sum sq = 0.0d0
С
        read each pix-perm and process
        do 10 frow = 1, nrows
          felem=1
          nelem=1
          inull=0
          colnum=4
          call ftgcve(iunit,colnum,frow,felem,nelem,enull,sum,
                      anyflq, status)
     &
          if (status .ne. 0) goto 99
          colnum=5
          call ftgcve(iunit,colnum,frow,felem,nelem,enull,sum2,
                      anyflg, status)
     &
          if (status .ne. 0) goto 99
          colnum=3
          call ftqcvj(iunit,colnum,frow,felem,nelem,inull,nobs,
                      anyflg,status)
     &
          if (status .ne. 0) goto 99
          if (nobs .gt. 0) then
            nperm = nperm + 1
            npoint = npoint + nobs
            sumsum = sumsum + sum
            sum sq = sum sq + sum2
          endif
10
        continue
С
        print out statistics
        print 1000, nperm, npoint, sumsum/dble(npoint),
                    sqrt(sum sq/dble(npoint))
        format(' Pix-perms read in = ',i9/
1000
               ' Total observations = ',i9/
                          Data mean = ',2x,f14.6/
     &
                           Data RMS = ',2x,f14.6)
С
        now close the table and quit
        call ftclos(iunit, status)
99
        if (status .le. 0) then
                print *,'*** Program completed successfully ***'
        else
С
           get the error text description
```

```
call ftgerr(status,errtxt)
    print *,'*** ERROR - program did not run successfully ***'
    print *,'status =',status,': ',errtxt
    end if
100 continue
end
```

```
program skymap
С
        A simple program to read the FITS binary table from the DMR
С
        skymap Initial Product.
        integer maxdim
        parameter (maxdim = 20)
        character*30 errtxt, extnam,
                      ttype (maxdim),
     &
                      tform (maxdim),
     &
                      tunit(maxdim)
     &
        logical simple, extend, anyflg
        integer iunit, status, bitpix, naxis, naxes (maxdim), pcount, gcount
        integer group, fpixel, nelem, nrows
        integer i, j, nobs, npseen, tfield, rwstat, bksize, vardat
        integer colnum, frow, felem
        integer hdutyp, inull
                temp, enull, tmax, tmin
        real
        doubleprecision sum, sum sq
        status=0
        iunit=15
С
        open the existing FITS file with readonly access
        rwstat=0
        call ftopen(iunit,'dmr skymap 31a.fits',rwstat,bksize,status)
        if (status .ne. 0) goto 99
        read the required primary array keywords
C
        call ftghpr(iunit, maxdim, simple, bitpix, naxis, naxes,
                     pcount, gcount, extend, status)
        if (status .ne. 0) goto 99
С
        now move to the binary table extension
        call ftmahd(iunit, 2, hdutyp, status)
        if (status .ne. 0) goto 99
С
        get the binary table parameters
        call ftghbn(iunit, maxdim, nrows, tfield, ttype, tform, tunit,
                     extnam, vardat, status)
        if (status .ne. 0) goto 99
С
        test that this is a DMR skymap dataset, and its fields
        are as expected.
        if (extnam .ne. 'DMR SKYMAP' .or.
            ttype(2) .ne. 'SIGNAL' .or.
            ttype(3) .ne. 'N OBS') then
          print *, 'extnam = ', extnam
          print *, 'ttype(2) = ', ttype(2)
```

```
print *, 'ttype(3) = ', ttype(3)
          stop 'Not a DMR skymap.'
        endif
С
        initialize statistical accumulators
        npseen = 0
            = 0.0d0
        sum
        sum sq = 0.0d0
               = -1e30
        tmax
              = 1e30
        tmin
С
        read each pixel and process
        do 10 frow = 1, nrows
          felem=1
          nelem=1
          inull=0
          colnum=2
          call ftgcve(iunit,colnum,frow,felem,nelem,enull,temp,
                      anyflg, status)
     &
          if (status .ne. 0) goto 99
          colnum=3
          call ftqcvj(iunit,colnum,frow,felem,nelem,inull,nobs,
                      anyflg, status)
     &
          if (status .ne. 0) goto 99
          if (nobs .gt. 0) then
            npseen = npseen + 1
                 = sum + temp
            sum
            sum sq = sum sq + temp*temp
            tmax = max(tmax, temp)
            tmin = min(tmin, temp)
          endif
10
        continue
С
        print out statistics
        print 1000, npseen,
     &
                    tmax,
                    tmin,
     &
                    sum/dble(npseen),
     &
                    sqrt( (dble(npseen)*sum sq - sum*sum)
     &
                           /dble(npseen)/dble(npseen-1) )
        format(' Observed Pixels = ',2x,i5/
1000
                             Max = ', f14.6/
     &
                             Min = ', f14.6/
     &
                             Avg = ', f14.6/
     &
                            Sigma = ', f14.6)
С
        now close the table and quit
        call ftclos(iunit, status)
99
        if (status .le. 0)then
                print *,'*** Program completed successfully ***'
        else
С
           get the error text description
           call ftgerr(status,errtxt)
```

```
print *,'*** ERROR - program did not run successfully ***'
    print *,'status =',status,': ',errtxt
    end if

100    continue
    end
```